

## **IMAGEPRINT BLACK for Windows Complete Install**

It is strongly recommended that you disable any anti-virus software prior to installing. You may need to reboot your computer one to two times as part of the install process.

1. Confirm that you've received your License Code email, and have the information handy. You'll enter the license code number in Step 8 below. Do not insert the USB dongle yet. You'll be prompted to do so after step 4.
2. Double-click **ImagePrint\_Installer.exe** to begin the installation.
3. Read the License Agreement, check the box for "I Agree", then click **Install**.
4. Installation files will be copied to your computer. During this process you may be prompted to reboot the computer one or two times, after which the installation will continue.
5. When prompted, insert the silver dongle into any free USB port on your computer or a USB hub.
6. The **IPSetup** utility will automatically launch.
7. In IPSetup, click **Add Printer**, then click **Continue** in the next window that appears.
8. Copy and paste the license code number from the email you received during the Activation step.
9. Select the printer model that you wish to install from the drop down menu and click **Continue**.
10. Type in a name for the printer or use the provided default.
11. If this is the computer that will be communicating with the printer, choose **Yes (Host Computer)**. (In most cases, this is the proper selection.)  
  
[For information on IMAGEPRINT Remote Client printing, please see chapter 2 of the IMAGEPRINT Manual.](#)
12. Click **Continue**.

13. Depending on the printer, you will see one or more of the following three options:

- **System Printer**

If you are presented with a list of installed system drivers, pick the one used by the printer you are installing.

- **Local Port**

If the printer is connected via USB, select this option and then click the **PORTS...** button in this section. Next, choose the driver for your printer and click **OK**.

- **Local Network**

If the printer connection is via the network (Ethernet or Wifi), click **Local Network** and provide the IP Address of the printer. This must be a static (unchanging) address.

[In most cases you can determine the IP Address of the printer and set it to Static \(sometimes called Manual or Panel\) via its front menu panel. Check your printer manual for specific information.](#)

14. Click **Done** to complete the printer configuration.

15. Close IPSetup by clicking the close (X) button in the upper right corner of the window.

16. Choose to **Quit** to exit the installer, or choose **Launch** to get started with IMAGEPRINT BLACK right away.

Whenever you want to use IMAGEPRINT Black you can start it by clicking your Windows Start Menu and choosing **IMAGEPRINT** from the **ColorByte Software** program group. You can also launch IMAGEPRINT Black directly from the IMAGEPRINT folder within your "Program Files (x86)" folder.

## **RECOMMENDED**

Before you make your first print, we suggest you read through "Making your first print with IMAGEPRINT BLACK" located in your IMAGEPRINT folder.

## **Additional Documentation**

The complete IMAGEPRINT manual is a valuable reference for getting the most out of your software. You'll find a copy in the IMAGEPRINT folder (IMAGEPRINT Users Manual.pdf) or by choosing **Manual** from the IMAGEPRINT Help menu.